

# YOLO GUIDE

Last Update: June 2025

## Table of Contents

<b>1</b>	<b>PREREQUISITES</b>	<b>3</b>
<b>1.1</b>	<b>PYTHON</b>	<b>3</b>
1.1.1	CHECK YOUR PYTHON VERSION	3
<b>1.2</b>	<b>VIRTUAL ENVIRONMENT</b>	<b>3</b>
1.2.1	WINDOWS	3
1.2.2	LINUX	4
<b>1.3</b>	<b>PACKAGES AND SOFTWARE REQUIREMENTS</b>	<b>4</b>
1.3.1	WINDOWS	4
1.3.2	LINUX	5
1.3.3	CUDA TOOLKIT	7
<b>2</b>	<b>TRAINING DATA</b>	<b>8</b>
<b>2.1</b>	<b>IMAGE COLLECTION</b>	<b>8</b>
<b>2.2</b>	<b>ROBOFLOW</b>	<b>9</b>
2.2.1	CREATE AN ACCOUNT	9
2.2.2	CREATE A PROJECT	9
2.2.3	ADD IMAGES TO THE PROJECT	10
2.2.4	ANNOTATE YOUR IMAGES	10
2.2.5	REVIEW ANNOTATIONS	15
2.2.6		18
2.2.7	ADDING IMAGES TO THE DATASET	19
2.2.8	CREATE THE FINAL TRAINING SET	20
2.2.9		23
2.2.10	DOWNLOAD THE DATASET	24
<b>3</b>	<b>TRAINING A MODEL</b>	<b>25</b>
3.1.1	CREATE A MODEL FOR PYTHON	25
3.1.2	CONVERT MODEL TO WORK WITH C++	26
<b>4</b>	<b>MODEL INFERENCE</b>	<b>27</b>

<b>4.1</b>	<b>PYTHON</b>	<b>27</b>
<b>4.2</b>	<b>C++</b>	<b>27</b>

# 1 PREREQUISITES

## 1.1 PYTHON

Install Python 3.8+ (*I used python 3.10 (windows) and 3.11 (rasberry py)*)

[Install python here](#)

---

### 1.1.1 Check your python version

In the command prompt, run `python --version` to check which version you have installed.

## 1.2 VIRTUAL ENVIRONMENT

Navigate to a folder where you will run all yolo code and create a virtual environment. The virtual environment is a safe place for installing packages and running yolo.

If you skip this step, you may break your system packages and have issues later on.

---

### 1.2.1 Windows

`dir` – command to print the contents of the current directory

`cd` – command to change to other directories

---

#### Create a virtual environment

Make sure you are in a folder you can locate later, the virtual environment will be created locally

```
python -m venv environment_name
```

**NOTE:** Add `--system-site-packages` option to give venv access to globals

---

#### Open the virtual environment

First, navigate to the folder where the venv was created

```
.\environment_name\Scripts\activate
```

---

#### Close the virtual environment

```
deactivate
```

---

## 1.2.2 Linux

ls – command to print the contents of the current directory

cd – command to change to other directories

---

### Create a virtual environment

Make sure you are in a folder you can locate later, the virtual environment will be created locally

```
python -m venv environment_name
```

**NOTE:** Add “--system-site-packages” option to give venv access to globals

---

### Open the virtual environment

First, navigate to the folder where the venv was created

```
source environment_name/bin/activate
```

---

### Close the virtual environment

```
deactivate
```

## 1.3 PACKAGES AND SOFTWARE REQUIREMENTS

---

### 1.3.1 Windows

---

#### Pip

Install pip if you do not already have it...

Update it if you do have it:

```
python -m pip install --upgrade pip
```

---

#### Ultralytics


```
pip install ultralytics
```

## PyTorch

Use this website <https://pytorch.org/get-started/locally/> to get the correct command.

```
pip install torch torchvision torchaudio --index-url https://download.pytorch.org/whl/cu128
```

I selected version 12.8 because my cuda drivers require it later on...



### 1.3.2 Linux

## Pip

Install pip if you do not already have it...

Update it if you do have it:

```
python -m pip install --upgrade pip
```

## Ultralytics

```
pip install ultralytics
```

## PyTorch

Use this website <https://pytorch.org/get-started/locally/> to get the correct command.

```
pip install torch torchvision torchaudio --index-url https://download.pytorch.org/whl/cu128
```

I selected version 12.8 because my cuda drivers require it later on...

PyTorch Build	Stable (2.7.0)		Preview (Nightly)	
Your OS	Linux	Mac	Windows	
Package	Pip	LibTorch	Source	
Language	Python		C++ / Java	
Compute Platform	CUDA 11.8	CUDA 12.6	CUDA 12.8	ROCM 6.3
Run this Command:	<pre>pip3 install torch torchvision torchaudio --index-url https://download.pytorch.org/whl/cu128</pre>			

---

### 1.3.3 Cuda Toolkit

Install the Cuda Toolkit here <https://developer.nvidia.com/cuda-downloads>


NOTE: you may require an older version if you have an older gpu

## 2 TRAINING DATA

The training data consists of images with bounding rectangles around the objects in the image you wish to identify. No knowledge of computer vision required.

### 2.1 IMAGE COLLECTION

I used my robot's camera to collect around 100 images of the Evac Zone from a few different angles. The images contain a mix of one or more of the objects.



The images can contain full or partial views of the objects.

Hint: this can be done quickly with a program that saves an image when you press space bar



## 2.2 ROBOFLOW



Per Ultralytics suggestion, I used roboflow to create the training data.

*I previously wrote a program to create the training data manually, but RCJ does not require development anymore so I will be showcasing a much simpler method.*

### 2.2.1 Create an account

Create an account [here on roboflow](#)

### 2.2.2 Create a project

	<p>Create a new project in the Project tab</p>
	<p>Select <b>Object Detection</b> as the project type.</p> <p>Name the project and give a name to the group of items you can try to detect (i.e. <i>victims</i>)</p>

### 2.2.3 Add images to the project

Upload the folder with all the images captured on from your robot

### 2.2.4 Annotate your images

Annotating your images is the process of identifying the objects in your uploaded images. All you need to do is draw bounding boxes around your images and specify the class it belongs to.


I will share some helpful notes for annotating.


#### How to get started

Navigate to the **annotate** page and select **annotate images** in the top right

<p>How do you want to label your images? <span>×</span></p> <div> <p><b>Start Labeling</b></p> <p>You and your team label your own images with help from our AI labeling tools.</p> <p><span>Start Labeling</span></p> </div>	<p>When prompted, select to annotate the images manually. This is the easiest way to annotate the first time</p>
---	--


## Annotation Interface

	<p>To annotate, simply click and drag to make boxes around the object you wish to detect later on.</p>
--	--




Make sure each bounding box you make is associated with the correct class label.

You can create any class name you want with the **annotation editor**.




Once your classes are created, you can use the keyboard number and the enter key to quickly classify the objects in your images.


**OR** you can just click the correct class with your mouse



The **drag tool** on the left side can be used to select and modify any of the bounding rectangles you have made.







Select the ***bounding box tool*** again to begin creating bounding boxes.



Use the arrows at the top of the screen to move between images.


## Annotation Tips

	<p>Use <i>tight</i> bounding boxes</p>
	<p>Do not cut off any of the object!!</p>
	<p>Annotate objects even if they are only partially visible</p>
	<p>Annotate objects even if they are overlapping</p>

## 2.2.5 Review Annotations

When you are done annotating the images, you must submit them for “review”.

Note: for the demo, I did not annotate the full set of images, but **it is highly recommended that you annotate all of your images**





You can easily take a look at your annotated images.

**NOTICE:** all images say “Train”... this will be modified later automatically when the training set is split

## Submit for review



This process is designed for groups of people to work on a project together. You will need to review your own annotations and approve them yourself.





## Review and approve one at a time

Select one of the images in the “**To Do**” tab and you can begin reviewing the images one at a time. You can make any modifications you want to fix the annotations.

	<p>Select any image to start the review</p>
	<p>Modify the annotations as needed.</p> <p>Then approve the image when you are satisfied.</p>

## Review and approve all at once


Return For Edits
Add Approved to Dataset

To Do 182
Approved 0
Rejected 0

Sort By
Newest

Annotated (40)

☒ Approve All
☐ Reject All



You can approve all annotated images at once and then add them to the dataset.

### 2.2.6

## 2.2.7 Adding images to the dataset

Check your approved images, if you are satisfied you can add the approved images to a dataset.

### Add Images To Dataset

Total Images to Add: 55

Method What's Train, Valid, Test?

Split Images Between Train/Valid/Test

**Train** 70%  
**Valid** 20%  
**Test** 10%

Image Distribution

Train: 39 images  
 Valid: 11 images  
 Test: 5 images

You are about to add 55 images to the dataset.  
47 images will be sent back as part of a new job.

**IMPORTANT:** select the method that will automatically split your dataset into the 3 categories “train” “valid” and “test”

Train – training images for the model

Valid – images used during training to validate the progress of the model and provide feedback

Test- images to test the model’s performance after the training is complete

## 2.2.8 Create the final training set

Pay close attention to the options shown below!!

**You can choose to modify these optional settings as you see fit for your training set.**

*You can redo this at any time with new options selected.*

RESUME LINE

demo\_yolo

Object Detection

DATA

Upload Data

Annotate

Dataset 55

**Versions** Train

Analytics

Classes & Tags

MODELS

Models

Visualize

Versions

Train a Model

To train a model, first create a new version of your dataset. Choose your dataset settings to get started.

Versions

No versions created yet.

Create New Version

Prepare your images and data for training by compiling them into a version. Experiment with different configurations to achieve better training results.

Source Images

Images: 55

Classes: 5

Unannotated: 0

Train/Test Split

Training Set: 39 images




Validation Set: 11 images

Testing Set: 5 images

Navigate to the “**Versions**” tab.



## Augmentation

<div> <div>4</div> <h3>Augmentation</h3> <p>What can augmentation do?</p> <p>Create new training examples for your model to learn from by generating augmented versions of each image in your training set.</p> <div> + Add Augmentation Step </div> <div> Continue Clear All </div> </div>	<p>The current training images can be augmented and modified to create new training images for different environmental conditions.</p>
<div> <h4>Brightness</h4> <div>  0% </div> <div> Add variability to image brightness to help your model be more resilient to lighting and camera setting changes. <div> 0% 20% 99% </div> <div> <input checked="" type="checkbox"/> Brighten <input checked="" type="checkbox"/> Darken </div> </div> <div>  -20%  20% </div> <div> Go Back Apply </div> </div>	<p>Adds images to the training dataset with augmented lighting conditions.</p> <p>You can select how much the dataset will be augmented.</p>
<div> <div>4</div> <h3>Augmentation</h3> <p>What can augmentation do?</p> <p>Create new training examples for your model to learn from by generating augmented versions of each image in your training set.</p> <div> <div> Brightness Between -20% and +20% Edit </div> <div> + Add Augmentation Step </div> </div> <div> Continue Clear All </div> </div>	<p>You can add more augmented images if you would like</p>



## Finalize the dataset

<div style="display: flex; align-items: center;"> <div style="border: 1px solid purple; border-radius: 50%; width: 30px; height: 30px; display: flex; align-items: center; justify-content: center; margin-right: 10px;">5</div> <div> <p><b>Create</b></p> <p>Review your selections and select a version size to create a moment-in-time snapshot of your dataset with the applied transformations.</p> <p>Larger versions take longer to train but often result in better model performance. <a href="#">See how this is calculated</a></p> <p>Maximum Version Size</p> <div style="border: 1px solid #ccc; padding: 2px; display: flex; align-items: center;"> <span>133 images (3x)</span> <span style="margin-left: 10px;">▼</span> </div> <div style="background-color: #8e44ad; color: white; padding: 5px; text-align: center; margin-top: 5px;">Create</div> </div> </div>	<p>Finalize and create the dataset.</p> <p>Select the number of variations you would like to create for each of your augmentation steps.</p> <p><b>NOTE:</b> if you do not select any augmentations, you will not have this option.</p>
--	---

### 2.2.9

## 2.2.10 Download the dataset

Once you are done, a dataset will be available for download.



Download and **extract the training data** to any folder you want



## 3 TRAINING A MODEL

To train the model I ran the program on a computer different from my robot.


I am using visual studio code on a computer with a Nvidia GPU. *Training times will be significantly slowing if you train using a cpu*

### 3.1.1 Create a model for python

First, create a model for python use (.pt pytorch model) and then if you want, you can convert it later for use with a c++ file

#### Virtual Environment

Make sure you have the correct virtual environment selected.



Select the venv in the bottom right corner of VS code

#### Data path

To train a model with your own custom dataset, you need to specify the correct path to the data.

If you open the folder that you downloaded, you should see a **data.yaml** file. This is the file needed to train a model.

test	✓	6/1/2025 12:48 PM	File folder	
train	↻	6/1/2025 12:48 PM	File folder	
valid	↻	6/1/2025 12:48 PM	File folder	
data	✓	6/1/2025 12:47 PM	Yaml Source File	1 KB
README.robotflow	✓	6/1/2025 12:47 PM	Text Document	2 KB

## Code (GPU TRAINING)

<pre>from ultralytics import YOLO</pre>	Import the necessary libraries
<pre>if __name__ == "__main__":</pre>	<p><b>THIS NEEDS TO BE INSIDE</b> a python main or it wont work</p>
<pre>    data_path = "path to training data as a string"      # using a model from yolov8     model = YOLO('yolov8n.yaml')      # custom training     results = model.train(data = data_path,                           imgsz = 320,                           device = 0,                           pretrained=False)      # save the pytorch model     model.save("model100.pt")</pre>	<p><b>PATH IS TO THE data.yaml file</b></p> <p>Create a model based on YOLOv8</p> <p>Train the model with your own custom data using a path to your data from roboflow</p> <p><b>imgsz = 320</b> because images from my robot will be 320x240</p> <p><b>device = 0</b> means GPU training (you can use <b>device = "cpu"</b> as well)</p> <p><b>pretrained = False</b> trains the model from scratch</p>
	<p>Save the pytorch mode. You can name it whatever you want.</p>

### 3.1.2 Convert Model to work with C++

.pt models work with python, not c++

Convert the model to an **onnx** file to work in **c++**

<pre>from ultralytics import YOLO  if __name__ == "__main__":     model = YOLO("model100.pt")     model.export(format = "tflite", imgsz = 320)</pre>	
--	--

## 4 MODEL INFERENCE

### 4.1 PYTHON

### 4.2 C++

Add this to the geany **Build > Set Build Commands**

Add this to the end of **C++ Commands (Build)**

`-l:libopencv_dnn.so`

Set Build Commands			
#	Label	Command	V
<b>C++ commands</b>			
1.	Compile	<code>g++ -Wall -c "%f"</code>	
2.	Build	<code>g++ -l:libopencv_dnn.so</code>	